**Why is my Linux server saying that it has run out of disk space when it hasn't?**

Article Number: 53 | Rating: 1/5 from 3 votes | Last Updated: Wed, Aug 18, 2021 at 1:55 PM

If you get an error message that tells you there is no space on the device when trying to create a file or directory, but check the disk usage and see that there is free space, it may be that your server has run out of inodes. Each file on t uses one inode.Â  If you have a very large number of small files, it may be that while you haven't used up all the spa server, you have used up all the inodes. You can check for inode usage by entering in this command: df -i To free up inodes, you will need to delete the excess files.Â  If you are unable to locate where these excess files are, you can ru command like this: for i in `find / -type d 2>/dev/null `; do echo `ls -a $i 2>/dev/null | wc -l ` $i; done | sort -n This will l directories on your server, and order them by the number of files they contain.Â  This can take a long time to run, de on the number of directories in your file system. Once you locate where the largest number of files are, you can remo files.Â  You should be able to upload files now.

Posted - Tue, Mar 3, 2015 at 3:59 PM.

Online URL:
https://www.heartinternet.uk/support/article/why-is-my-linux-server-saying-that-it-has-run-out-of-disk-space-when-it-h



PDF Generated by PHPKB Knowledge Base Script